

NAME

wimlib-imagex-join – Join split WIMs into a standalone one-part WIM

SYNOPSIS

wimlib-imagex join [*OPTION...*] *OUT_WIMFILE SPLIT_WIM_PART...*

DESCRIPTION

Joins the *SPLIT_WIM_PART*s into a standalone one-part WIM *OUT_WIMFILE*. This command is also available as simply **wimjoin** if the appropriate hard link or batch file has been installed.

All parts of the split WIM must be specified. You probably want to do so using a shell wildcard.

wimlib-imagex join can join both non-pipable and pipable split WIMs.

OPTIONS**--check**

When reading each *SPLIT_WIM_PART*, verify its integrity if the integrity table is present; additionally, when writing *OUT_WIMFILE*, write an integrity table. If this option is not specified, an integrity table will be included in *OUT_WIMFILE* if and only if one was present in the first part of the split WIM.

EXAMPLES

Join a split WIM, with the parts named ‘windows*.swm’ where the * is anything (usually the number of the part, except for the first part which may have no number), and write the joined WIM to the file ‘windows.wim’.

```
wimlib-imagex join windows.wim windows*.swm
```

NOTES

wimlib-imagex join is roughly equivalent to:

```
wimlib-imagex export SWM_PART_1 --ref="SWM_GLOB" all OUT_WIMFILE
```

SEE ALSO

wimlib-imagex(1) **wimlib-imagex-export(1)**