

**NAME**

wimlib-imagex-optimize – Optimize a WIM archive

**SYNOPSIS**

**wimlib-imagex optimize** *WIMFILE* [*OPTION...*]

**DESCRIPTION**

**wimlib-imagex optimize** will rebuild the stand-alone WIM *WIMFILE*. The new WIM is written to a temporary file, and it is renamed to the original file when it's ready. This action will remove any holes that have been left as a result of appending images, so the new WIM may be slightly smaller than the old WIM. In addition, some errors in the original WIM may be fixed by re-writing it (although most cannot). This command is also available as simply **wimoptimize** if the appropriate hard link or batch file has been installed.

**OPTIONS****--check**

When reading *WIMFILE*, verify its integrity if an integrity table is present. In addition, include an integrity table in the optimized WIM. If this option is not specified, by default the integrity table (if present) is not checked, and an integrity table is included in the rebuilt WIM if and only if one was present in the original WIM.

**--nocheck**

Neither verify the integrity of *WIMFILE* using the integrity table, nor include an integrity table in the rebuilt WIM file.

**--recompress**

Recompress all compressed streams in *WIMFILE* when rebuilding it. This will increase the time needed to rebuild the WIM, unless the WIM is uncompressed, but it may result in a better compression ratio if wimlib can do a better job than the program that wrote the original file. A side effect of this is that every stream in the original WIM will be checksummed, so this can help verify that the WIM is intact (equivalent to applying all the images from it).

**--compress=TYPE[:LEVEL]**

Recompress the WIM file using the specified compression type, and optionally the specified compression level for that compression type. This implies **--recompress**.

See the documentation for this option to **wimlib-imagex capture** (1) for more details.

**--chunk-size=SIZE**

Set the WIM compression chunk size to *SIZE*. See the documentation for this option to **wimlib-imagex capture** (1) for more details.

**--solid**

Create a "solid" archive that compresses multiple files together. This can result in a higher compression ratio, but has disadvantages such as reduced compatibility. See the documentation for this option to **wimlib-imagex capture** (1) for more details.

**--solid-chunk-size=SIZE**

Like **--chunk-size**, but set the chunk size used in solid blocks. See the documentation for this option to **wimlib-imagex capture** (1) for more details.

**--solid-compress=TYPE[:LEVEL]**

Like **--compress**, but set the compression type used in solid blocks. See the documentation for this option to **wimlib-imagex capture** (1) for more details.

**--threads=NUM\_THREADS**

Number of threads to use for compressing data. Default: autodetect (number of processors). This parameter is only meaningful when **--recompress** is also specified.

**--pipable**

Rebuild the WIM so that it can be applied fully sequentially, including from a pipe. See **wimlib-imagex capture**(1) for more details about creating pipable WIMs. By default, when neither

**--pipable** or **--not-pipable** is specified, the rebuilt WIM will be pipable if and only if it was already pipable.

**--not-pipable**

Rebuild the WIM in the non-pipable format. (This is the default if *WIMFILE* is not pipable.)

**NOTES**

**wimlib-imagex optimize** does not support split WIMs.

**wimlib-imagex optimize** is roughly equivalent to:

**wimlib-imagex export** *WIMFILE* all tmp.wim && mv tmp.wim *WIMFILE*

**SEE ALSO**

**wimlib-imagex(1)** **wimlib-imagex-export(1)** **wimlib-imagex-verify(1)**